



FIPS 140-2 Non-Proprietary Security Policy

CryptoComply™ | Server

Software Version 2.1

Document Version 1.3

October 18, 2013



SafeLogic Inc.

530 Lytton Avenue, Ste. 200

Palo Alto, CA 94301

www.safelogic.com

Abstract

This document provides a non-proprietary FIPS 140-2 Security Policy for CryptoComply | Server.

Table of Contents

| | | |
|----------|--|-----------|
| 1 | Introduction | 5 |
| 1.1 | About FIPS 140 | 5 |
| 1.2 | About this Document | 5 |
| 1.3 | External Resources | 5 |
| 1.4 | Notices | 5 |
| 1.5 | Acronyms | 5 |
| 2 | CryptoComply Server | 7 |
| 2.1 | Cryptographic Module Specification | 7 |
| 2.1.1 | Validation Level Detail | 7 |
| 2.1.2 | Approved Cryptographic Algorithms | 7 |
| 2.1.3 | Non-Approved Cryptographic Algorithms | 8 |
| 2.2 | Module Interfaces | 8 |
| 2.3 | Roles, Services, and Authentication | 10 |
| 2.3.1 | Operator Services and Descriptions | 10 |
| 2.3.2 | Operator Authentication | 11 |
| 2.4 | Physical Security | 11 |
| 2.5 | Operational Environment | 11 |
| 2.6 | Cryptographic Key Management | 12 |
| 2.6.1 | Random Number Generation | 14 |
| 2.6.2 | Key/Critical Security Parameter (CSP) Authorized Access and Use by Role and Service/Function | 14 |
| 2.6.3 | Key/CSP Storage | 14 |
| 2.6.4 | Key/CSP Zeroization | 14 |
| 2.7 | Self-Tests | 14 |
| 2.7.1 | Power-On Self-Tests | 15 |
| 2.7.2 | Conditional Self-Tests | 16 |
| 2.7.3 | Cryptographic Function | 16 |
| 2.8 | Mitigation of Other Attacks | 16 |
| 3 | Guidance and Secure Operation | 17 |
| 3.1 | Crypto Officer Guidance | 17 |
| 3.1.1 | Software Installation | 17 |
| 3.1.2 | Additional Rules of Operation | 17 |
| 3.2 | User Guidance | 17 |
| 3.2.1 | General Guidance | 17 |

List of Tables

| | |
|--|----|
| Table 1 – Acronyms and Terms..... | 6 |
| Table 2 – Validation Level by FIPS 140-2 Section..... | 7 |
| Table 3 – FIPS-Approved Algorithm Certificates..... | 8 |
| Table 4 – Logical Interface / Physical Interface Mapping | 10 |
| Table 5 – Module Services, Roles, and Descriptions..... | 11 |
| Table 6 – Module Keys/CSPs..... | 13 |
| Table 7 – Power-On Self-Tests | 15 |
| Table 8 – Conditional Self-Tests..... | 16 |

List of Figures

| | |
|---|---|
| Figure 1 – Module Boundary and Interfaces Diagram | 9 |
|---|---|

1 Introduction

1.1 About FIPS 140

Federal Information Processing Standards Publication 140-2 — Security Requirements for Cryptographic Modules specifies requirements for cryptographic modules to be deployed in a Sensitive but Unclassified environment. The National Institute of Standards and Technology (NIST) and Communications Security Establishment Canada (CSEC) Cryptographic Module Validation Program (CMVP) run the FIPS 140 program. The NVLAP accredits independent testing labs to perform FIPS 140 testing; the CMVP validates modules meeting FIPS 140 validation. *Validated* is the term given to a module that is documented and tested against the FIPS 140 criteria.

More information is available on the CMVP website at <http://csrc.nist.gov/groups/STM/cmvp/index.html>.

1.2 About this Document

This non-proprietary Cryptographic Module Security Policy for the CryptoComply | Server from SafeLogic provides an overview of the product and a high-level description of how it meets the security requirements of FIPS 140-2. This document contains details on the module's cryptographic keys and critical security parameters. This Security Policy concludes with instructions and guidance on running the module in a FIPS 140-2 mode of operation.

SafeLogic CryptoComply | Server may also be referred to as the “module” in this document.

1.3 External Resources

The SafeLogic website (<http://www.safelogic.com>) contains information on SafeLogic services and products. The Cryptographic Module Validation Program website contains links to the FIPS 140-2 certificate and SafeLogic contact information.

1.4 Notices

This document may be freely reproduced and distributed in its entirety without modification.

1.5 Acronyms

The following table defines acronyms found in this document:

| Acronym | Term |
|------------|--|
| AES | Advanced Encryption Standard |
| ANSI | American National Standards Institute |
| API | Application Programming Interface |
| CMVP | Cryptographic Module Validation Program |
| CO | Crypto Officer |
| CSEC | Communications Security Establishment Canada |
| CSP | Critical Security Parameter |
| DES | Data Encryption Standard |
| DH | Diffie-Hellman |
| DSA | Digital Signature Algorithm |
| EC | Elliptic Curve |
| EMC | Electromagnetic Compatibility |
| EMI | Electromagnetic Interference |
| FCC | Federal Communications Commission |
| FIPS | Federal Information Processing Standard |
| GPC | General Purpose Computer |
| GUI | Graphical User Interface |
| HMAC | (Keyed-) Hash Message Authentication Code |
| KAT | Known Answer Test |
| MAC | Message Authentication Code |
| MD | Message Digest |
| NIST | National Institute of Standards and Technology |
| OS | Operating System |
| PKCS | Public-Key Cryptography Standards |
| PRNG | Pseudo Random Number Generator |
| PSS | Probabilistic Signature Scheme |
| RNG | Random Number Generator |
| RSA | Rivest, Shamir, and Adleman |
| SHA | Secure Hash Algorithm |
| SSL | Secure Sockets Layer |
| Triple-DES | Triple Data Encryption Algorithm |
| TLS | Transport Layer Security |
| USB | Universal Serial Bus |

Table 1 – Acronyms and Terms

2 CryptoComply | Server

2.1 Cryptographic Module Specification

CryptoComply | Server is a standards-based “Drop-in Compliance™” cryptographic engine for servers and appliances. The module delivers core cryptographic functions to server platforms and features robust algorithm support, including Suite B algorithms. CryptoComply offloads secure key management, data integrity, data at rest encryption, and secure communications to a trusted implementation.

The module's logical cryptographic boundary is the shared library files and their integrity check HMAC files. The module is a multi-chip standalone embodiment installed on a General Purpose Device.

All operations of the module occur via calls from host applications and their respective internal daemons/processes. As such there are no untrusted services calling the services of the module.

2.1.1 Validation Level Detail

The following table lists the level of validation for each area in FIPS 140-2:

| FIPS 140-2 Section Title | Validation Level |
|--|------------------|
| Cryptographic Module Specification | 1 |
| Cryptographic Module Ports and Interfaces | 1 |
| Roles, Services, and Authentication | 1 |
| Finite State Model | 1 |
| Physical Security | N/A |
| Operational Environment | 1 |
| Cryptographic Key Management | 1 |
| Electromagnetic Interference / Electromagnetic Compatibility | 1 |
| Self-Tests | 1 |
| Design Assurance | 1 |
| Mitigation of Other Attacks | N/A |

Table 2 – Validation Level by FIPS 140-2 Section

2.1.2 Approved Cryptographic Algorithms

The module's cryptographic algorithm implementations have received the following certificate numbers from the Cryptographic Algorithm Validation Program:

| Algorithm | CAVP Certificate |
|--|------------------|
| AES | 2273 |
| HMAC-SHA-1, HMAC-SHA-224, HMAC-SHA-256, HMAC-SHA-384, HMAC-SHA-512 | 1391 |
| DSA, DSA 2 | 709 |
| ECDSA, ECDSA2 | 368 |
| RSA (X9.31, PKCS #1.5, PSS) | 1166 |
| SHA-1, SHA-224, SHA-256, SHA-384, SHA-512 | 1954 |
| Triple-DES | 1420 |
| RNG (ANSI X9.31) | 1132 |
| SP 800-90 DRBG (Hash_DRBG, HMAC_DRBG, CTR_DRBG, Dual_EC_DRBG) | 281 |
| CVL (ECC CDH KAS) | 44 |

Table 3 – FIPS-Approved Algorithm Certificates

2.1.3 Non-Approved Cryptographic Algorithms

The module supports the following non-FIPS 140-2 approved but allowed algorithms:

- RSA encrypt/decrypt with key sizes of 1024-15360 bits (key wrapping; key establishment methodology provides between 80 and 256 bits of encryption strength)
- EC Diffie-Hellman (key establishment methodology provides between 80 and 256 bits of encryption strength)

2.2 Module Interfaces

The figure below shows the module's physical and logical block diagram:




Figure 1 – Module Boundary and Interfaces Diagram

The interfaces (ports) for the physical boundary include the computer keyboard port, mouse port, network port, USB ports, display and power plug. When operational, the module does not transmit any information across these physical ports because it is a software cryptographic module. Therefore, the module’s interfaces are purely logical and are provided through the Application Programming Interface (API) that a calling daemon can operate. The logical interfaces expose services that applications directly call, and the API provides functions that may be called by a referencing application (see Section 2.3 – Roles, Services, and Authentication for the list of available functions). The module distinguishes between logical interfaces by logically separating the information according to the defined API.

The API provided by the module is mapped onto the FIPS 140- 2 logical interfaces: data input, data output, control input, and status output. Each of the FIPS 140- 2 logical interfaces relates to the module’s callable interface, as follows:

| FIPS 140-2 Interface | Logical Interface | Module Physical Interface |
|----------------------|---|-------------------------------------|
| Data Input | Input parameters of API function calls | Network Interface |
| Data Output | Output parameters of API function calls | Network Interface |
| Control Input | API function calls | Keyboard Interface, Mouse Interface |
| Status Output | For FIPS mode, function calls returning status information and return codes provided by API function calls. | Display Controller |
| Power | None | Power Supply |

Table 4 – Logical Interface / Physical Interface Mapping

As shown in Figure 1 – Module Boundary and Interfaces Diagram and Table 5 – Module Services, Roles, and Descriptions, the output data path is provided by the data interfaces and is logically disconnected from processes performing key generation or zeroization. No key information will be output through the data output interface when the module zeroizes keys.

2.3 Roles, Services, and Authentication

The module supports a Crypto Officer and a User role. The module does not support a Maintenance role. The User and Crypto-Officer roles are implicitly assumed by the entity accessing services implemented by the Module.

2.3.1 Operator Services and Descriptions

The module supports services that are available to users in the various roles. All of the services are described in detail in the module’s user documentation. The following table shows the services available to the various roles and the access to cryptographic keys and CSPs resulting from services:

| Service | Roles | CSP / Algorithm | Permission |
|---------------------------------|----------------|--------------------------------------|-----------------------------|
| Module initialization | Crypto Officer | None | CO: execute |
| Symmetric encryption/decryption | User | AES Key, Triple-DES ¹ Key | User: read/write/execute |
| Digital signature ² | User | RSA Private Key, DSA Private Key | User: read/write/execute |
| Symmetric key generation | User | AES Key, Triple-DES Key | User: read/write/execute |

¹ Two-key Triple-DES is restricted and only available for legacy use in accordance with SP800-131A.

² Note that per SP800-131A, issuing 1024-bit signatures with SHA-1 is deprecated currently and disallowed at the end of 2013.

| | | | |
|---------------------------|------------------------|---|-----------------------------|
| Asymmetric key generation | User | RSA Private Key, DSA Private Key | User: read/write/execute |
| Keyed Hash (HMAC) | User | HMAC Key HMAC SHA-1, HMAC SHA- 224, HMAC SHA-256, HMAC SHA-384, HMAC SHA-512 | User: read/write/execute |
| Message digest (SHS) | User | SHA-1, SHA-224, SHA-256, SHA-384, SHA-512 | User: read/write/execute |
| Random number generation | User | PRNG Seed and Seed Key | User: read/write/execute |
| Show status | Crypto Officer User | None | User and CO: execute |
| Self test | User | All CSPs | User: read/execute |
| Zeroize | Crypto Officer User | All CSPs | CO: read/write/execute |

Table 5 – Module Services, Roles, and Descriptions

2.3.2 Operator Authentication

As required by FIPS 140-2, there are two roles (a Crypto Officer role and User role) in the module that operators may assume. As allowed by Level 1, the module does not support authentication to access services. As such, there are no applicable authentication policies. Access control policies are implicitly defined by the services available to the roles as specified in Table 5 – Module Services, Roles, and Descriptions.

2.4 Physical Security

This section of requirements does not apply to this module. The module is a software-only module and does not implement any physical security mechanisms.

2.5 Operational Environment

The module operates on a general purpose computer (GPC) running a general purpose operating system (GPOS). For FIPS purposes, the module is running on this operating system in single user mode and does not require any additional configuration to meet the FIPS requirements.

The module was tested on the following platforms:

- Apple Mac OS X 10.8 on a MacBook Air
- Microsoft Windows Server 2008 R2 on a Dell Optiplex 755

- Red Hat Enterprise Linux 6.3 on a Dell Optiplex 755
- CentOS 6.3 on a Dell Optiplex 755
- SUSE Linux Enterprise 11SP2 on a Dell Optiplex 755

Compliance is maintained for other versions of the respective operating system family where the binary is unchanged. No claim can be made as to the correct operation of the module or the security strengths of the generated keys when ported to an operational environment which is not listed on the validation certificate.

The GPC(s) used during testing met Federal Communications Commission (FCC) FCC Electromagnetic Interference (EMI) and Electromagnetic Compatibility (EMC) requirements for business use as defined by 47 Code of Federal Regulations, Part15, Subpart B. FIPS 140-2 validation compliance is maintained when the module is operated on other versions of the GPOS running in single user mode, assuming that the requirements outlined in NIST IG G.5 are met.

2.6 Cryptographic Key Management

The table below provides a complete list of Critical Security Parameters used within the module:

| Keys and CSPs | Storage Locations | Storage Method | Input Method | Output Method | Zeroization | Access |
|-----------------|-------------------|----------------|--------------------|---------------|-----------------------|-------------------|
| AES Key | RAM | Plaintext | API call parameter | None | power cycle cleanse() | CO: RWD U: RWD |
| Triple-DES Key | RAM | Plaintext | API call parameter | None | power cycle cleanse() | CO: RWD U: RWD |
| RSA Public Key | RAM | Plaintext | API call parameter | None | power cycle cleanse() | CO: RWD U: RWD |
| RSA Private Key | RAM | Plaintext | API call parameter | None | power cycle cleanse() | CO: RWD U: RWD |
| DSA Public Key | RAM | Plaintext | API call parameter | None | power cycle cleanse() | CO: RWD U: RWD |
| DSA Private Key | RAM | Plaintext | API call parameter | None | power cycle cleanse() | CO: RWD U: RWD |
| HMAC Key | RAM | Plaintext | API call parameter | None | power cycle cleanse() | CO: RWD U: RWD |

| | | | | | | |
|---------------------------------|---------------|-----------|--------------------|------|-----------------------|-------------------|
| PRNG Seed | RAM | Plaintext | API call parameter | None | power cycle cleanse() | CO: RWD U: RWD |
| PRNG Seed Key | RAM | Plaintext | API call parameter | None | power cycle cleanse() | CO: RWD U: RWD |
| Integrity Key | Module Binary | Plaintext | None | None | None | CO: RWD U: RWD |
| EC DSA Private Key | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| EC DSA Public Key | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| EC DH Public Components | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| EC DH Private Components | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| EC DRBG Entropy | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| EC DRBG S Value (Seed Length) | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| EC DRBG init_seed | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| HMAC DRBG Entropy | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| HMAC DRBG V Value (Seed Length) | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| HMAC DRBG Key | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |
| HMAC DRBG init_seed | RAM | Plaintext | None | None | power cycle cleanse() | CO: RWD U: RWD |

R = Read W = Write D = Delete

Table 6 – Module Keys/CSPs

The application that uses the module is responsible for appropriate destruction and zeroization of the key material. The module provides functions for key allocation and destruction which overwrite the memory that is occupied by the key information with zeros before it is deallocated.

2.6.1 Random Number Generation

The module uses ANSI X9.31 and DRBG for creation of asymmetric and symmetric keys.

The module accepts input from entropy sources external to the cryptographic boundary for use as seed material for the module's Approved RNGs. This external entropy source provides an estimated minimum amount of 93 bits of entropy, which limits the strength of the generated key.

The module performs continual tests on the random numbers it uses to ensure that the seed and seed key input to the Approved RNG do not have the same value. The module also performs continual tests on the output of the approved RNG to ensure that consecutive random numbers do not repeat.

2.6.2 Key/Critical Security Parameter (CSP) Authorized Access and Use by Role and Service/Function

An authorized application as user (the User role) has access to all key data generated during the operation of the module.

2.6.3 Key/CSP Storage

Public and private keys are provided to the module by the calling process and are destroyed when released by the appropriate API function calls or during power cycle. The module does not perform persistent storage of keys.

2.6.4 Key/CSP Zeroization

The application is responsible for calling the appropriate destruction functions from the API. The destruction functions then overwrite the memory occupied by keys with zeros and deallocates the memory. This occurs during process termination / power cycle. Keys are immediately zeroized upon deallocation, which sufficiently protects the CSPs from compromise.

2.7 Self-Tests

FIPS 140-2 requires that the module perform self tests to ensure the integrity of the module and the correctness of the cryptographic functionality at start up. In addition some functions require continuous verification of function, such as the random number generator. All of these tests are listed and described in this section. In the event of a self-test error, the module will log the error and will halt. The module must be initialized into memory to resume function.

The following sections discuss the module's self-tests in more detail.

2.7.1 Power-On Self-Tests

Power-on self-tests are executed automatically when the module is loaded into memory. The module verifies the integrity of the runtime executable using a HMAC-SHA1 digest computed at build time. If the fingerprints match, the power-up self-tests are then performed. If the power-up self-test is successful, a flag is set to place the module in FIPS mode.

| TYPE | DETAIL |
|---------------------------------|---|
| Software Integrity Check | <ul style="list-style-type: none"> • HMAC-SHA1 on all module components |
| Known Answer Tests ³ | <ul style="list-style-type: none"> • AES encrypt/decrypt • AES GCM • AES CCM • XTS-AES • AES CMAC • Triple-DES CMAC • ECDH • HMAC-SHA1 • HMAC-SHA224 • HMAC-SHA256 • HMAC-SHA384 • HMAC-SHA512 • RSA • SHA-1 • SHA-224 • SHA-256 • SHA-384 • SHA-512 • X9.31 RNG • SP 800-90 DRBG (Hash_DRBG, HMAC_DRBG, CTR_DRBG, Dual_EC_DRBG) • Triple-DES encrypt/decrypt • ECC CDH |
| Pair-wise Consistency Tests | <ul style="list-style-type: none"> • DSA • RSA • ECDSA |

Table 7 – Power-On Self-Tests

Input, output, and cryptographic functions cannot be performed while the Module is in a self-test or error state because the module is single-threaded and will not return to the calling application until the power-up self tests are complete. If the power-up self tests fail, subsequent calls to the module will also fail - thus no further cryptographic operations are possible.

³ Note that all SHA-X KATs are tested as part of the respective HMAC SHA-X KAT. SHA-1 is also tested independently.

2.7.2 Conditional Self-Tests

The module implements the following conditional self-tests upon key generation, or random number generation (respectively):

| TYPE | DETAIL |
|-----------------------------|---|
| Pair-wise Consistency Tests | <ul style="list-style-type: none"> • DSA • RSA • ECDSA |
| Continuous RNG Tests | <ul style="list-style-type: none"> • Performed on all approved PRNGs |

Table 8 – Conditional Self-Tests

2.7.3 Cryptographic Function

All security functions and cryptographic algorithms are performed in Approved mode. There is no non-FIPS mode of operation.

The module verifies the integrity of the runtime executable using a HMAC-SHA1 digest which is computed at build time. If this computed HMAC-SHA1 digest matches the stored, known digest, then the power-up self-test (consisting of the algorithm-specific Pairwise Consistency and Known Answer tests) is performed. If any component of the power-up self-test fails, an internal global error flag is set to prevent subsequent invocation of any cryptographic function calls. Any such power-up self test failure is a hard error that can only be recovered by reinstalling the module⁴. The power-up self-tests may be performed at any time by reloading the module.

No operator intervention is required during the running of the self-tests.

2.8 Mitigation of Other Attacks

The Module does not contain additional security mechanisms beyond the requirements for FIPS 140-2 Level 1 cryptographic modules.

⁴ The initialization function could be re-invoked but such re-invocation does not provide a means from recovering from an integrity test or known answer test failure

3 Guidance and Secure Operation

3.1 Crypto Officer Guidance

3.1.1 Software Installation

The module is provided directly to solution developers and is not available for direct download to the general public. The module and its host application is to be installed on an operating system specified in Section 2.5 or one where portability is maintained.

There is no non-FIPS mode. The module only provides a FIPS mode of operation.

3.1.2 Additional Rules of Operation

1. The writable memory areas of the module (data and stack segments) are accessible only by the application so that the operating system is in "single user" mode, i.e. only the application has access to that instance of the module.
2. The operating system is responsible for multitasking operations so that other processes cannot access the address space of the process containing the module.

3.2 User Guidance

3.2.1 General Guidance

The module is not distributed as a standalone library and is only used in conjunction with the solution.

The end user of the operating system is also responsible for zeroizing CSPs via wipe/secure delete procedures.

If the module power is lost and restored, the calling application can reset the IV to the last value used.